

Purpose:

The purpose of this guide is how to resolve the error mentioned below regarding the SDS Nesting plug-in for the VMD software.

Error

Your time has elapsed, contact SDS

Message:

Solution:

1. Navigate to and delete this file.
C:\ControllerData\Utilities\misc\VmdNest.vmd
2. A Windows service will recreate the file within a few seconds. Behind the scenes, this service creates the file when it attempts to link VMDNest to the database and set the User Account. It only does this one time.
3. After VMDNest.vmd appears, wait 30 seconds for the Database to complete its tasks.
4. Restart Windows "The HMI."
5. Let the system finish rebooting, finish launching VMD, and connect to the controller. Check VMDNest.